

Istruzioni per l'Upgrade della Licenza Easylabel / Instructions for Easylabel License Upgrade

1. Utilizzo di EASYLABEL License Tool

- Se l'utente utilizza un computer con Windows 10 o Windows 11, può installare l'applicazione EASYLABEL License Tool, avviarla con la chiave hardware (dongle) inserita, e cliccare su "Create License File" per generare un file .rtc.
- Il tool è scaricabile da questo link: <https://easylabel.com/download/drivers/EASYLABEL-License-Tool.exe>
- Il License Tool può essere installato anche se sul PC è presente una versione precedente di EASYLABEL, oppure se EASYLABEL non è installato. È sufficiente soddisfare i requisiti di sistema (Windows 10 o 11) e avere installata l'applicazione License Tool per poter verificare i contenuti della licenza.

2. Utilizzo del vecchio Key ID Tool (per versioni 6.2 – 6.4)

- a. Aprire EASYLABEL
- b. Menu Help > Check for Upgrades → si aprirà il Key ID Tool
- c. Cliccare su "Create RTC file" → il file .rtc verrà generato automaticamente sul desktop locale

3. Generazione di un file .wbc (alternativa)

- Su qualsiasi PC, se il sistema è più datato oppure se il dongle è vuoto (e quindi non riconosciuto dagli altri tool), è possibile creare un file .wbc, che funziona come un file .rtc.
- ■■ Nota: questo metodo è più complesso perché richiede l'accesso alle impostazioni avanzate di WibuKey nel Pannello di Controllo di Windows. Per questo motivo è consigliato solo se le altre due opzioni non funzionano.
- Fare riferimento al video allegato come guida alla procedura di creazione del file .wbc.

[GUARDA IL VIDEO TUTORIAL](#)

■ Nota importante

- È indispensabile che la chiave hardware (dongle) sia collegata e riconosciuta dal PC per poter generare correttamente il file di licenza.
- Se il dongle non è collegato o non viene rilevato, il file di licenza non verrà creato o verrà generato in modo errato.

1. Using the EASYLABEL License Tool

- If the user is on a Windows 10 or Windows 11 computer, they can install the EASYLABEL License Tool, run it with the license dongle plugged in, and click "Create License File" to generate an .rtc file.
- The License Tool can be downloaded here: <https://easylabel.com/download/drivers/EASYLABEL-License-Tool.exe>
- Users can still install and use the License Tool if they have older versions of EASYLABEL installed, or no EASYLABEL at all. As long as they meet the OS requirements (Windows 10 or 11) and have the License Tool application installed, they can check their license contents.

2. Using the old Key ID Tool (for versions 6.2 – 6.4)

- a. Open EASYLABEL
- b. Go to Help > Check for Upgrades → the Key ID Tool will open
- c. Click "Create RTC file" → the .rtc file will then be generated on the local desktop

3. Generating a .wbc file (alternative option)

- On any PC, if it is older or if the dongle is blank (and therefore not recognized by the tools), you can create a .wbc file, which acts just like an .rtc file.
- ■■ Note: this file is a bit more complicated to generate as it goes into the Advanced settings of WibuKey in the Windows Control Panel, so it is not typically recommended unless the other two options have been tried first.
- Please see the attached video for reference regarding generating a .wbc file.

[CHECK THE VIDEO TUTORIAL](#)

■ Important Reminder

- The license dongle must be plugged in and recognized by the PC in order to generate the license file correctly.
- If the dongle is not plugged in or not communicating, the license file will either not be created or will be created incorrectly.